

# TDT506: Computer Networks

Instructor: Niklas Carlsson

Email: [niklas.carlsson@liu.se](mailto:niklas.carlsson@liu.se)

Notes derived from "*Computer Networking: A Top Down Approach*", by Jim Kurose and Keith Ross, Addison-Wesley.



The slides are adapted and modified based on slides from the book's companion Web site, as well as modified slides by Anirban Mahanti and Carey Williamson.

# What is Wireless Networking?

- ❖ The use of infra-red (IR) or radio frequency (RF) signals to share information and resources between devices
- ❖ Promises *anytime, anywhere* connectivity
  - Laptops, palmtops, PDAs, Internet-enabled phone promise anytime *untethered* Internet access
- ❖ No wires!



# What is Wireless Networking?

- ❖ The use of infra-red (IR) or radio frequency (RF) signals to share information and resources between devices
- ❖ Promises *anytime, anywhere* connectivity
  - Laptops, palmtops, PDAs, Internet-enabled phones promise anytime *untethered* Internet access
- ❖ No wires!



# What is Wireless Networking?

- ❖ The use of infra-red (IR) or radio frequency (RF) signals to share information and resources between devices
- ❖ Promises *anytime, anywhere* connectivity
  - Laptops, palmtops, PDAs, Internet-enabled phones promise anytime *untethered* Internet access
- ❖ No wires!
- ❖ Lots of media buzzwords!
  - Mobile Internet, Pervasive Computing, Nomadic Computing, M-Commerce, Ubiquitous Computing ...
  - ... and acronyms; e.g., CSMA, WiFi, 802.11, ...






# Two important (but different!) challenges

# Two important (but different!) challenges

- ❖ Communication over wireless link
- ❖ Handling mobile user who changes point of attachment to network

# Two important (but different!) challenges

- ❖ Communication over wireless link




- ❖ Handling mobile user who changes point of attachment to network




# Two important (but different!) challenges

- ❖ Communication over wireless link



- ❖ Handling mobile user who changes point of attachment to network





# Wireless Link Characteristics

Differences from wired link ...


- **Decreasing signal strength:** radio signal attenuates as it propagates through matter (path loss)
- **Interference from other sources:** standardized wireless network frequencies (e.g., 2.4 GHz) shared by other devices (e.g., phone); devices (motors) interfere as well
- **Multi-path propagation:** radio signal reflects off objects ground, arriving at destination at slightly different times

.... make communication across (even a point to point) wireless link much more "difficult"

- Higher error rates; lower bandwidths; non-uniform transmission characteristics; increased usage costs; and increased susceptibility to interference and eavesdropping

# Wireless Link Characteristics

- ❖ SNR: signal-to-noise ratio
  - larger SNR - easier to extract signal from noise (a "good thing")
- ❖ *SNR versus BER tradeoffs*
  - *given physical layer:* increase power → increase SNR → decrease BER
  - *given SNR:* choose physical layer that meets BER requirement, giving highest throughput
    - SNR may change with mobility: dynamically adapt physical layer (modulation technique, rate)



- ..... QAM256 (8 Mbps)
- - - QAM16 (4 Mbps)
- BPSK (1 Mbps)




# Technology and Example Standards

- ❖ The right technology/standard for the problem/environment??

# A Classification of Networks

- ❖ Wide Area Network (WAN)
- ❖ Metropolitan Area Network (MAN)
- ❖ Local Area Network (LAN)
  
- ❖ Wireless LAN (WLAN)
- ❖ Home Networks
- ❖ Personal Area Network (PAN)
- ❖ Body Area Network (BAN)
- ❖ Also ... Ad hoc and sensor networks ...

# Characteristics of selected wireless link standards





# Differences in "per hop bandwidths" primarily from ...

## ❖ Physical layer

- Spectrum allocation (wave length)
- Frequency; channel width; time multiplexing
- Signal-to-Noise; BER; Error correction; etc.

## ❖ MAC layer (sub-layer in data link layer)

- Multiple access techniques
- E.g., FDMA, TDMA, CDMA, SDMA, CSMA

# Frequency band spectrum

- ❖ spectrum allocated by global and national agencies

(Less sensitive to obstacles)  
Low frequency

(More sensitive to obstacles)  
High frequency



ELF (30-300Hz)


Telephone;  
AM broadcast  
Cell phone;  
Satellite

Visible light  
(400-900THz)

Microwave links




# Infrastructure Mode



## Infrastructure mode

- ❑ base station connects mobiles into wired network
- ❑ handoff: mobile changes base station providing connection into wired network

# Ad hoc Mode




## Ad hoc mode

- ❑ no base stations
- ❑ nodes can only transmit to other nodes within link coverage
- ❑ nodes organize themselves into a network: route among themselves



# 802.11 LAN architecture




- Wireless host communicates with base station
  - base station = access point (AP)
- Basic Service Set (BSS) (aka "cell") in infrastructure mode contains:
  - wireless hosts
  - access point (AP)
  
  - ad hoc mode: hosts only

# Wireless Cells


- ❖ 802.11b has 11 channels
- ❖ Channels 1, 6, and 11 are non-overlapping

- ❖ Admin chooses frequency for AP






# Wireless Cells



- ❖ 802.11b has 11 channels
- ❖ Channels 1, 6, and 11 are non-overlapping
- ❖ Each AP coverage area is called a "cell"
- ❖ Wireless nodes can roam between cells


- ❖ Admin chooses frequency for AP
- ❖ Interference possible: channel can be same as that chosen by neighboring AP!



# 802.11: Channels, association


- ❖ host: must *associate* with an AP
  - scans channels, listening for *beacon frames* containing AP's name (SSID) and MAC address
  - selects AP to associate with
  - may perform authentication
  - will typically run DHCP to get IP address in AP's subnet

# 802.11: passive/active scanning



## Passive Scanning:

- (1) **Beacon** frames sent from APs
- (2) **Association Request** frame sent: H1 to selected AP
- (3) **Association Response** frame sent: H1 to selected AP



## Active Scanning:

- (1) **Probe Request** frame broadcast from H1
- (2) **Probes Response** frame sent from APs
- (3) **Association Request** frame sent: H1 to selected AP
- (4) **Association Response** frame sent: H1 to selected AP



# IEEE 802.11: multiple access

- ❖ avoid collisions: 2+ nodes transmitting at same time
- ❖ 802.11: CSMA - sense before transmitting
  - don't collide with ongoing transmission by other node
- ❖ 802.11: *no* collision detection!
  - difficult to receive (sense collisions) when transmitting due to weak received signals (fading)
  - can't sense all collisions in any case: hidden terminal, fading
  - goal: *avoid collisions*: CSMA/C(ollision)A(voidance)


# IEEE 802.11 MAC Protocol: CSMA/CA

## 802.11 sender

- 1 if sense channel idle for **DIFS** then transmit entire frame (no CD)
- 2 if sense channel busy then start random backoff time  
timer counts down while channel idle  
transmit when timer expires
- 3 if no **ACK** then increase random backoff interval, repeat step 2


## 802.11 receiver

- if frame received OK  
return **ACK** after **SIFS**  
(service model is connectionless, acked)





# IEEE 802.11 MAC: DCF, cont'd

- Priority-based scheme - use 3 values for IFS:
  - SIFS (short IFS): shortest IFS used for immediate responses such as ACK, CTS, poll response
  - PIFS (point coordination function IFS): middle length IFS used for issuing polls by a centralized controller
  - DIFS (distributed coordination function IFS): longest IFS used for regular asynchronous frames



# Hidden Terminal Problem

Hidden terminal problem (ad-hoc and WLAN)








# Hidden Terminal Problem

## Hidden terminal problem (ad-hoc and WLAN)

A wants to send to B  
but cannot hear that  
B is busy




# Hidden Terminal Problem



Hidden terminal problem (ad-hoc and WLAN)

- medium free near the transmitter
- medium not free near the receiver

=> *Packet collision*



A wants to send to B  
but cannot hear that  
B is busy



# Hidden Terminal Problem


Hidden terminal problem (ad-hoc and WLAN)

- medium free near the transmitter
- medium not free near the receiver



=> *Packet collision*

Possible solution:

- MAC scheme using RTS-CTS scheme





A wants to send to B  
but cannot hear that  
B is busy



# Wireless Network Characteristics

Multiple wireless senders and receivers create additional problems (beyond multiple access):



Hidden terminal problem

- A and B can hear each other
- B and C can hear each other
- A and C can't hear each other
- thus A and C are unaware of their interference at B

Signal fading:

- A and B hear each other
- B and C hear each other
- A and C can't hear each other interfering at B

# Avoiding collisions (more)

*idea:* allow sender to "reserve" channel rather than random access of data frames: avoid collisions of long data frames



# Avoiding collisions (more)

*idea:* allow sender to “reserve” channel rather than random access of data frames: avoid collisions of long data frames

- ❖ sender first transmits *small* request-to-send (RTS) packets to base station using CSMA
  - RTS may still collide with each other (but they're short)
- ❖ BS broadcasts clear-to-send CTS to host in response to RTS
- ❖ RTS heard by all nodes because of broadcast property
  - sender transmits (large) data frame
  - other stations defer transmissions until it is done

Avoid data frame collisions completely  
using small reservation packets!

# Collision Avoidance: RTS-CTS exchange



# Exposed Terminal Problems


Exposed terminal problem - ad-hoc and WLAN

- medium free near the receiver
- medium busy near the transmitter  
=> *Waist of bandwidth*

Possible solutions:

- directional antennas
- separate channels for control and data


B wants to send to C  
but mistakenly thinks  
the transmission will fail







# 802.11 frame: addressing




**Address 1:** MAC address of wireless host or AP to receive this frame

**Address 2:** MAC address of wireless host or AP transmitting this frame


**Address 3:** MAC address of router interface to which AP is attached

**Address 3:** used only in ad hoc mode

# 802.11 frame: addressing



# 802.11 frame: more







# 802.11: advanced capabilities

## *Rate Adaptation*

- ❖ base station, mobile dynamically change transmission rate (physical layer modulation technique) as mobile moves, SNR varies



1. SNR decreases, BER increase as node moves away from base station
2. When BER becomes too high, switch to lower transmission rate but with lower BER

# 802.11: advanced capabilities

## *Power Management*

- ❑ node-to-AP: "I am going to sleep until next beacon frame"
  - AP knows not to transmit frames to this node
  - node wakes up before next beacon frame
- ❑ beacon frame: contains list of mobiles with AP-to-mobile frames waiting to be sent
  - Every 100ms (250 $\mu$ s wakeup time)
  - node will stay awake if AP-to-mobile frames to be sent; otherwise sleep again until next beacon frame
  - Explicit pull request


Note: Nodes with nothing to send/receive can save 99% of energy






# Bluetooth Networking: Piconets and Scatternets

- Bluetooth devices are organized in *piconets*
  - Up to eight devices can be part of a piconet
- Devices are divided in *master* and *slaves*
  - Master controls the utilization of the radio channel (e.g. frequency-hopping sequence and timing)
  - Slaves may communicate only with the master and when allowed by the master
- Several connected piconets is called a *scatternet*
  - A device may belong to different piconets, and may be both a master and a slave in two different piconets



# 802.15: personal area network (PAN)

- ❖ less than 10 m diameter
- ❖ replacement for cables (mouse, keyboard, headphones)
- ❖ ad hoc: no infrastructure
- ❖ master/slaves:
  - slaves request permission to send (to master)
  - master grants requests
- ❖ 802.15: evolved from Bluetooth specification
  - 2.4-2.5 GHz radio band
  - up to 721 kbps



- (M) Master device
- (S) Slave device
- (P) Parked device (inactive)

# Two Popular 2.4 GHz Standards:

## ❖ IEEE 802.11 (WiFi)

- Fast (11 Mbps)
- High power
- Long range
- Single-purpose
- Typically channel 1, 6, or 11
- Ethernet replacement
- Easily available



## ❖ Bluetooth





- Slow (1 Mbps)
- Low power
- Short range
- Flexible
- Frequency hopping
- Cable replacement (e.g., device-to-device)



# Interference example

## Measurements (Mahanti et al. 2010)



- ❖ Many devices and technologies sharing the medium






# 802.16: WiMAX (MAN)

- ❖ like 802.11 & cellular:  
base station model
  - transmissions to/from base station by hosts with omnidirectional antenna
  - base station-to-base station backhaul with point-to-point antenna
- ❖ unlike 802.11:
  - range ~ 6 miles ("city rather than coffee shop")
  - ~14 Mbps



# 802.16: WiMAX: downlink, uplink scheduling

- ❖ transmission frame
  - down-link subframe: base station to node
  - uplink subframe: node to base station



base station tells nodes who will get to receive (DL map) and who will get to send (UL map), and when

- WiMAX standard provide mechanism for scheduling, but not scheduling algorithm





# Background: Cellular network technology

## ❖ Overview

- 1G: Analog voice (no global standard ...)
- 2G: Digital voice (again ... GSM vs. CDMA)
- 3G: Digital voice and data
  - Again ... UMTS (WCDMA) vs. CDMA2000 (both CDMA-based)
  - and ... 2.5G: EDGE (GSM-based)
- 4G: LTE, LTE-Advanced (IP-based only) ...
  - OFDM (OFDMA for downlink and SC-OFDM for uplink)

## ❖ Trends

- More data, packet-based switching, shared channel, directional (spatial reuse), multi-antenna, etc.
- Other goals: Seamless with other technologies, QoS for multimedia, etc.


# Components of cellular network architecture

## cell

- ❖ covers geographical region
- ❖ *base station* (BS) analogous to 802.11 AP
- ❖ *mobile users* attach to network through BS
- ❖ *air-interface*: physical and link layer protocol between mobile and BS

## MSC


- ❖ connects cells to wired tel. net.
- ❖ manages call setup (more later!)
- ❖ handles mobility (more later!)




# Cellular networks: the first hop

Techniques for sharing mobile-to-BS radio spectrum


- ❖ **combined FDMA/TDMA:** divide spectrum in frequency channels, divide each channel into time slots
- ❖ **CDMA:** code division multiple access
- ❖ **SDMA:** space division multiple access




time slots




# 2G (voice) network architecture



# 3G (voice+data) network architecture




# 3G (voice+data) network architecture



# Code Division Multiple Access (CDMA)

- ❖ used in several wireless broadcast channels (cellular, satellite, etc) standards
- ❖ unique "code" assigned to each user; i.e., code set partitioning
- ❖ all users share same frequency, but each user has own "chipping" sequence (i.e., code) to encode data
- ❖ *encoded signal* = (original data) X (chipping sequence)
- ❖ *decoding*: inner-product of encoded signal and chipping sequence
- ❖ allows multiple users to "coexist" and transmit simultaneously with minimal interference (if codes are "orthogonal")



# CDMA Encode/Decode





# CDMA: two-sender interference

senders




# Practical chipping codes ...

- ❑ Orthogonal even under offset?
  - No synchronization ...
  - Random sequence; high probability low cross-correlation
- ❑ Different chip lengths?
  - different rates, take advantage of silence, more calls




# What is mobility?

- ❖ spectrum of mobility, from the *network* perspective:




# GSM: indirect routing to mobile




# GSM: handoff with common MSC

- ❖ Handoff goal: route call via new base station (without interruption)




# GSM: handoff between MSCs



(a) before handoff

- ❖ *anchor MSC*: first MSC visited during call
  - call remains routed through anchor MSC
- ❖ new MSCs add on to end of MSC chain as mobile moves to new MSC
- ❖ IS-41 allows optional path minimization step to shorten multi-MSC chain

# GSM: handoff between MSCs



(b) after handoff

- *anchor MSC*: first MSC visited during call
  - call remains routed through anchor MSC
- new MSCs add on to end of MSC chain as mobile moves to new MSC
- IS-41 allows optional path minimization step to shorten multi-MSC chain





More slides ...


# Components of cellular network architecture

## cell

- ❑ covers geographical region
- ❑ *base station* (BS) analogous to 802.11 AP
- ❑ *mobile users* attach to network through BS
- ❑ *air-interface*: physical and link layer protocol between mobile and BS

## MSC


- ❑ connects cells to wide area net
- ❑ manages call setup (more later!)
- ❑ handles mobility (more later!)



wired network

# Components of cellular networks, cont'd


- Frequency reuse: use the same frequency spectrum in different set of cells
- Cells that reuse the same frequency must be distant enough for avoiding interference
- Transmission power control
- Migration of a mobile station from one cell to another with continuance of communication -> *handoff*






# What is mobility?

- ❖ spectrum of mobility, from the *network* perspective:



# 802.11: mobility within same subnet

- ❖ H1 remains in same IP subnet: IP address can remain same
- ❖ switch: which AP is associated with H1?
  - self-learning (Ch. 5): switch will see frame from H1 and "remember" which switch port can be used to reach H1





# Mobility: Vocabulary

*home network:* permanent  
"home" of mobile  
(e.g., 128.119.40/24)

*home agent:* entity that will  
perform mobility functions on  
behalf of mobile, when mobile  
is remote

*permanent address:*  
address in home  
network, *can always* be  
used to reach mobile  
e.g., 128.119.40.186






# Mobility: more vocabulary


*permanent address:* remains constant (e.g., 128.119.40.186)

*visited network:* network in which mobile currently resides (e.g., 79.129.13/24)


*care-of-address:* address in visited network. (e.g., 79.129.13.2)



wide area network



*correspondent:* wants to communicate with mobile




*foreign agent:* entity in visited network that performs mobility functions on behalf of mobile.

# How do *you* contact a mobile friend:

Consider friend frequently changing addresses, how do you find her?

- ❖ search all phone books?
- ❖ call her parents?
- ❖ expect her to let you know where he/she is?



# Mobility: approaches


- ❖ *Let routing handle it:* routers advertise permanent address of mobile-nodes-in-residence via usual routing table exchange.
  - routing tables indicate where each mobile located
  - no changes to end-systems
- ❖ *Let end-systems handle it:*
  - *indirect routing:* communication from correspondent to mobile goes through home agent, then forwarded to remote
  - *direct routing:* correspondent gets foreign address of mobile, sends directly to mobile

# Mobility: approaches

- ❖ *Let routing handle it:* routers advertise permanent address of mobile, mobile advertises current residence via usual routing table exchange
  - routing table entries for each mobile location
  - no changes to end systems
- ❖ *let end-systems handle it:*
  - *indirect routing:* communication from correspondent to mobile goes through home agent, then forwarded to remote
  - *direct routing:* correspondent gets foreign address of mobile, sends directly to mobile

not  
scalable  
to millions of  
mobiles


# Mobility: registration



End result:


- ❖ Foreign Agent (FA) knows about mobile
- ❖ Home Agent (HA) knows location of mobile

# Mobility via Indirect Routing



# Indirect Routing: comments

- ❖ Mobile uses two addresses:
  - **permanent address**: used by correspondent (hence mobile location is *transparent* to correspondent)
  - **care-of-address**: used by home agent to forward datagrams to mobile
- ❖ foreign agent functions may be done by mobile itself
- ❖ **triangle routing**: correspondent-home-network-mobile
  - inefficient when correspondent, mobile are in same network




# Indirect Routing: moving between networks

- ❖ suppose mobile user moves to another network
  - registers with new foreign agent
  - new foreign agent registers with home agent
  - home agent update care-of-address for mobile
  - packets continue to be forwarded to mobile (but with new care-of-address)
- ❖ mobility, changing foreign networks transparent: *ongoing connections can be maintained!*




# Mobility via Direct Routing




# Mobility via Direct Routing: comments

- ❖ overcome triangle routing problem
- ❖ **non-transparent to correspondent:**  
correspondent must get care-of-address from home agent
  - what if mobile changes visited network?



# Accommodating mobility with direct routing

- ❖ anchor foreign agent: FA in first visited network
- ❖ data always routed first to anchor FA
- ❖ when mobile moves: new FA arranges to have data forwarded from old FA (chaining)



# Mobile IP


- ❖ RFC 3220
- ❖ has many features we've seen:
  - home agents, foreign agents, foreign-agent registration, care-of-addresses, encapsulation (packet-within-a-packet)
- ❖ three components to standard:
  - indirect routing of datagrams
  - agent discovery
  - registration with home agent




# Handling mobility in cellular networks

- ❖ *home network*: network of cellular provider you subscribe to (e.g., Sprint PCS, Verizon)
  - *home location register (HLR)*: database in home network containing permanent cell phone #, profile information (services, preferences, billing), information about current location (could be in another network)
- ❖ *visited network*: network in which mobile currently resides
  - *visitor location register (VLR)*: database with entry for each user currently in network
  - could be home network

# GSM: indirect routing to mobile




# GSM: handoff with common MSC



- ❖ Handoff goal: route call via new base station (without interruption)
- ❖ reasons for handoff:
  - stronger signal to/from new BSS (continuing connectivity, less battery drain)
  - load balance: free up channel in current BSS
  - GSM doesn't mandate why to perform handoff (policy), only how (mechanism)
- ❖ handoff initiated by old BSS




# GSM: handoff with common MSC



1. old BSS informs MSC of impending handoff, provides list of 1+ new BSSs
2. MSC sets up path (allocates resources) to new BSS
3. new BSS allocates radio channel for use by mobile
4. new BSS signals MSC, old BSS: ready
5. old BSS tells mobile: perform handoff to new BSS
6. mobile, new BSS signal to activate new channel
7. mobile signals via new BSS to MSC: handoff complete. MSC reroutes call
8. MSC-old-BSS resources released


# GSM: handoff between MSCs



(a) before handoff

- ❖ *anchor MSC*: first MSC visited during call
  - call remains routed through anchor MSC
- ❖ new MSCs add on to end of MSC chain as mobile moves to new MSC
- ❖ IS-41 allows optional path minimization step to shorten multi-MSC chain

# GSM: handoff between MSCs



(b) after handoff

- *anchor MSC*: first MSC visited during call
  - call remains routed through anchor MSC
- new MSCs add on to end of MSC chain as mobile moves to new MSC
- IS-41 allows optional path minimization step to shorten multi-MSC chain



More slides ...

# Wireless Networking Technologies

- ❖ Mobile devices - laptop, PDA, cellular phone, wearable computer, sensors, ...
- ❖ Operating modes
  - Infrastructure mode (Access Point (AP))
  - Ad hoc mode
- ❖ Access technology
  - Bluetooth (1 Mbps, up to 3m)
  - IEEE 802.11 (up to 54 Mbps, 20 - 100m)

# Chapter 6: Wireless and Mobile Networks

## Background:

- ❖ # wireless (mobile) phone subscribers now exceeds # wired phone subscribers!
- ❖ # wireless Internet-connected devices soon to exceed # wireline Internet-connected devices